

KB Name	How to transfer a viewON2 project to another PC		
Type	KB		
Since revision	NA		
KB Number	KB-0019-0	Build	10
Mod date	17. Oct 2008		


Knowledge Base Information

How to transfer a viewON2 project to another PC


This document will help you transfer a viewON project from your PC to another PC.

1 On your PC

In the directory C:\Program Files\viewON2\workspace, choose the project you would like to send to another PC. In our example, we will choose folder called "Test".



Right-click on the folder, click on **Send To** and choose **Compressed (zipped) Folder**.



KB Name	How to transfer a viewON2 project to another PC		
Type	KB		
Since revision	NA		
KB Number	KB-0019-0	Build	10
Mod date	17. Oct 2008		

Knowledge Base Information

If you have created your own Symbols (not predefined or modified), make sure you zip the **Symbols** folder as well. This is very important, otherwise, the animation will not work on other computers.

2 On another PC


Copy the zipped files in the directory C:\Program Files\viewON2\workspace and unzip them.

IMPORTANT



Bear in mind that viewON does not accept sub-folders in workspace. So make sure there is not a folder inside another folder. Besides, the name of the folder cannot be changed, otherwise, viewON will not find the project.

Copy and unzip the symbols in the **Symbols** directory of your viewON C:\Program Files\viewON\workspace\symbols.



In our example Switch2 and Reactor3 are symbols which have been modified and added in the Symbols directory for the animation to work.